

## Ubuntu File Server with simple Remote Power Control (V1.0)

The intended purpose of this unholy amalgamation of violent disregard for best practices is to make a simple local file share folder, removing the constant USB chasing with easy-to-use start and stop functions to avoid unnecessary power usage when not in use – for people for whom just want two easy buttons to press, and security is tertiary.

This project had two key goals it had to reach; it had to be simple enough for me to execute without much prior knowledge and even simpler for the end user to use. As I am writing this, I believe I have managed to do both. This guide is mainly made as practice and is not necessarily meant to be followed or installed by anyone.

Assumptions & Prerequisites	3
Dependencies	3
Security Concerns	4
Placeholders Used in this Guide	5
Guide Sections	6
A) Initial Server Setup & Checks	6
A.1: Verify or create user	6
A.2: SSH Server	6
A.3: Find Network Info	6
B) Network Configuration (Server & Client)	7
B.1: Configure Stable Server IP - Choose ONE method	7
B.3: Install Bonjour on client PC - Recommended	7
B.4: Define Connection Method	7
C) Remote Shutdown Setup	8
C.1: Configure Passwordless Sudo on Server	8
C.2: Generate SSH Key on Client PC	8
C.3: Install Public Key	8
C.4: Edit Stop, Server bat on your PC	9

D) Remote Startup Setup - Wake-on-LAN (Wol)	10
D.1: Enable WoL in server BIOS	10
D.2: Edit Start_Server.bat on your PC	10
E) File Share Setup with Samba	11
E.1: Install Samba on Server	11
E.2: Create Share Directory	11
E.3: Create Share Group & User	11
E.4: Set Directory Permissions	11
E.5.a: Enter Samba Share Configuration	11
E.5.b: Configure Samba Share	11
E.6. Restart Samba	12
E.7. Set Samba Password	12
F) Client Shortcut Setup - Optional	12
F.1. Prepare Client Folder	12
F.2 Version A: Create Shortcuts	12
F.2 Version B: Create & Pin Taskbar Shortcuts	13
G) Testing	14
G.1. Test Power Off	14
G.2. Test Power On	14
G.3. Test File Share	14



# Assumptions & Prerequisites:

- You have a server computer with Ubuntu Server (LTS version like 22.04 recommended) already installed.
- You have administrator access (a user account with sudo privileges) on the Ubuntu server.
- You have a Windows client PC on the same local network as the server.
- You have network infrastructure (router, switches) connecting the devices.
- You can download/transfer files to the Windows client PC.

# Dependencies:

#### On Server:

- Ubuntu Server LTS
- openssh-server (usually installed by default),
- samha
- avahi-daemon (recommended).

#### **On Windows Client:**

- PuTTY tools: puttygen.exe, plink.exe, pageant.exe.
   Use the included files or visit: <u>Download PuTTY: latest release (0.83)</u>
- WakeMeOnLan.exe or similar WoL utility.
   Use included or Download from NirSoft or trusted source.
- Apple Bonjour Print Services for Windows (recommended for .local hostname resolution). Download from Apple Support.

# **Security Concerns**

**WARNING:** This guide intentionally prioritizes simplicity and ease of use over standard security practices. It is designed for use on a trusted local network where security is a secondary concern. **Do NOT use this setup in untrusted environments or expose the server directly to the internet.** 

By following this guide, you accept the following known security risks:

- Passwordless Remote Shutdown: The remote shutdown method uses an SSH key without a passphrase and configures sudo to allow the poweroff command without requiring a password. This means:
- Anyone gaining access to the specific private key file (.ppk) on your client PC can shut down the server.
- If the client PC itself is compromised, the server could be shut down maliciously.

**Mitigation:** Protect the .ppk file diligently on your client computer.

- **Unencrypted SSH Key:** The SSH private key (.ppk file) is generated without a passphrase for automation convenience. Standard security practices recommend using a passphrase to protect the key file itself, which this guide skips.
- **Basic Service Configuration:** This guide implements only basic configurations for SSH and Samba (file sharing). It does **not** include common security hardening steps such as:
- Configuring a host firewall (like ufw) on the server.
- Advanced SSH server security tuning.
- Fine-grained Samba share permissions or security options beyond the essentials for basic access control

**Assumption of Trusted Network:** The entire setup assumes your local network (behind your router) is a trusted environment.

# Placeholders Used in this Guide:

#### <YOUR\_ADMIN\_USER>

The admin username on the Ubuntu server

#### • <YOUR\_SERVER\_HOSTNAME>

The desired hostname for the server

#### • <FINAL SERVER IP OR HOSTNAME>

The stable way to reach the server on the final network

Strongly recommended to use <YOUR\_SERVER\_HOSTNAME>.local
after completing Section B.

#### • <YOUR\_SERVER\_MAC>

The MAC address of the server's wired Ethernet port

#### • <INTERFACE\_NAME>

The server's network interface name

#### <YOUR\_SAMBA\_USER>

Username for accessing the file share

#### • <YOUR\_SAMBA\_SHARE\_NAME>

The name of the network share

#### • <YOUR\_SHARE\_PATH>

The path on the server where shared files are stored

#### <YOUR\_SHARE\_GROUP>

A Linux group to manage share permissions

#### • <CLIENT\_CONTROL\_FOLDER\_PATH>

The full path on the Windows client where control files are stored Example: (C:\ServerControl) Highly recommended to use this path

#### <FINAL\_SERVER\_IP>

The static or reserved DHCP IP address for the server

#### • <SUBNET\_MASK\_CIDR>

Subnet mask in CIDR notation Example: (24 for 255.255.25.0)

#### • <GATEWAY IP>

The router's IP address for the server's subnet.

#### <DNS\_IP\_1>, <DNS\_IP\_2>

IP addresses for DNS servers

## **Guide Sections:**

## A) Initial Server Setup & Checks

Ensure basic admin access and find network info

#### A.1: Verify or create user

Verify you have a user account with sudo rights. If not, create one and replace your admin user

Use: sudo adduser <YOUR\_ADMIN\_USER> to create new user, follow prompts and set a strong password

Then: sudo usermod -aG sudo <YOUR\_ADMIN\_USER>

Log in as this user for subsequent steps

#### A.2: SSH Server

Ensure SSH server is installed and running

Then do a: sudo apt update

Install with: sudo apt install openssh-server

Verify your system with: sudo systemctl status sshd

Which should be active and running

#### A.3: Find Network Info

Log into the server via console or initial SSH using DHCP IP

Find interface name: ip a and note down <INTERFACE\_NAME>

Find Netplan File: ls /etc/netplan/ and note down .yaml filename

Find MAC Address: ip link show <INTERFACE\_NAME> Note down <YOUR\_SERVER\_MAC>

## B) Network Configuration (Server & Client)

Stable server address/name & client discovery setup Skip this section if your server already has a stable IP/hostname setup you prefer.

#### **B.1: Configure Stable Server IP - Choose ONE method**

#### **B.1.a: DHCP Reservation – Recommended**

Use router interface to reserve <FINAL\_SERVER\_IP> for <YOUR\_SERVER\_MAC> Reboot server using: sudo reboot and verify

After the server reboots, SSH back in using the <FINAL\_SERVER\_IP> you reserved
Then run ip a to confirm the network interface shows that specific IP address

#### **B.1.b: Static IP - Fallback**

Edit netplan file: sudo nano /etc/netplan/FILE.yaml to set static <FINAL\_SERVER\_IP>, <SUBNET\_MASK\_CIDR>, <GATEWAY\_IP>, <DNS\_IP\_1>, <DNS\_IP\_2> for your <INTERFACE\_NAME>. Apply using: sudo netplan apply, reconnect via new IP, verify by entering: ip a

# B.2: Install Avahi on the server – Recommended sudo apt update && sudo apt install avahi-daemon

Allows discovery via <YOUR\_SERVER\_HOSTNAME>.local

#### B.3: Install Bonjour on client PC - Recommended

Install "Bonjour Print Services for Windows" from Apple and reboot if needed

#### **B.4: Define Connection Method**

For subsequent steps, <FINAL\_SERVER\_IP\_OR\_HOSTNAME> should be <YOUR\_SERVER\_HOSTNAME>.local Use <FINAL\_SERVER\_IP> only if .local fails testing later.

## C) Remote Shutdown Setup

Allow client to shut down server securely without password using SSH keys Skip if you only need Wake-on-LAN or have another shutdown method.

#### C.1: Configure Passwordless Sudo on Server

Allow <YOUR\_ADMIN\_USER> to run poweroff without password.

sudo nano /etc/sudoers.d/010\_adminuser-nopasswd-poweroff

Add line: <YOUR\_ADMIN\_USER> ALL=(ALL) NOPASSWD: /sbin/poweroff

Save and exit.

Set permissions: sudo chmod 440 /etc/sudoers.d/010\_adminuser-nopasswd-poweroff

Check syntax: sudo visudo -c

#### C.2: Generate SSH Key on Client PC

Use puttygen.exe. Click Generate - Leave passphrase blank recommended for simplicity according to the project's needs - protect the file well

Save **public key** text to

<CLIENT\_CONTROL\_FOLDER\_PATH>\Files\<YOUR\_ADMIN\_USER>\_shutdown\_key.pub
Save private key as

<CLIENT\_CONTROL\_FOLDER\_PATH>\Files\<YOUR\_ADMIN\_USER>\_shutdown\_key.ppk

#### C.3: Install Public Key

SSH into server as <YOUR\_ADMIN\_USER>. And run:

mkdir -p ~/.ssh && chmod 700 ~/.ssh

nano ~ /.ssh/authorized\_keys

Paste public key text from .pub file, Save/Exit

chmod 600 ~/.ssh/authorized\_keys

This sets file permissions so ONLY the file owner - <YOUR\_ADMIN\_USER> - can read and write the file. SSH requires this for security; it won't use key files accessible by others

#### C.4: Edit Stop\_Server.bat on your PC

Navigate to <CLIENT\_CONTROL\_FOLDER\_PATH>\Files\ and open Stop\_Server.bat in a text editor

Note: the following string needs to be on one line in the file but for obvious reasons it is split up here

<CLIENT\_CONTROL\_FOLDER\_PATH>\Files\plink.exe -i
<CLIENT\_CONTROL\_FOLDER\_PATH>\Files\<YOUR\_ADMIN\_USER>\_shutdown\_key.ppk -batch
<YOUR\_ADMIN\_USER>@ <YOUR\_SERVER\_HOSTNAME>.local sudo poweroff

Save and exit

**Note:** Using <YOUR\_SERVER\_HOSTNAME>.local is strongly recommended as it makes the script work even if the server's IP address changes (requires Avahi/Bonjour setup from Section B).

If .local resolution fails on your specific network, you must replace <YOUR\_SERVER\_HOSTNAME>.local in the command above with the specific static or reserved <FINAL\_SERVER\_IP> configured in Step B.1.

#### Example:

echo Sending Shutdown Signal to localdropbox.local...

C:\ServerControl\Files\plink.exe -i C:\ServerControl\Files\serveradmin\_shutdown\_key.ppk -batch serveradmin@localdropbox.local sudo poweroff echo Signal Sent. Please wait for server to power down. pause

Note: .local should be replaced with (192.168.1.xxx) if static IP route was chosen in Step B.1

# D) Remote Startup Setup - Wake-on-LAN (Wol)

Allow client to wake server from sleep/power-off - Skip if you only need remote shutdown.

#### D.1: Enable WoL in server BIOS

Reboot server, enter BIOS/UEFI setup by pressing bios key on boot screen (Usually F2, DEL) "Find Power Management" or "Network settings"
Enable "Wake on LAN" / "Power On by PCIe/PCI", or similar option
Save & Exit BIOS

#### D.2: Edit Start\_Server.bat on your PC

In <CLIENT\_CONTROL\_FOLDER\_PATH>\Files\Start\_Server.bat, ensure WakeMeOnLan command is: batch <CLIENT\_CONTROL\_FOLDER\_PATH>\Files\WakeMeOnLan.exe /wakeup <YOUR\_SERVER\_MAC> Use the correct MAC address found in A.3 Save and exit

From .bat file – less cluttered example:

echo Sending Wake-on-LAN signal to localdropbox (c8:0a:a9:1f:xx:xx)... C:\ServerControl\Files\WakeMeOnLan.exe /wakeup c8:0a:a9:1f:xx:xx echo Signal sent. pause

## E) File Share Setup with Samba

Create a network share accessible by a specific user - Skip if you don't need a file share or already have one.

#### E.1: Install Samba on Server

sudo apt update && sudo apt install samba

#### **E.2: Create Share Directory**

sudo mkdir -p <YOUR\_SHARE\_PATH>

Creates an directory <where you assign it>

#### E.3: Create Share Group & User

sudo groupadd <YOUR\_SHARE\_GROUP>

Creates a new Linux group used to manage share permissions

sudo adduser --system --no-create-home --ingroup <YOUR\_SHARE\_GROUP> --disabled-login --shell

/sbin/nologin <YOUR\_SAMBA\_USER>

Creates user without login shell/home

#### **E.4: Set Directory Permissions**

sudo chown root:<YOUR\_SHARE\_GROUP> <YOUR\_SHARE\_PATH>

sudo chmod 1770 <YOUR\_SHARE\_PATH>

Allows group members to add/delete their own files

#### E.5.a: Enter Samba Share Configuration

#### sudo nano /etc/samba/smb.conf

Allows you to enter nano and edit samba configurations

#### E.5.b: Configure Samba Share

Add the following section at the very end of the `/etc/samba/smb.conf` file Replace the bracketed placeholders (`<...>`) with your chosen names/paths:

[<YOUR\_SAMBA\_SHARE\_NAME>]

comment = Shared Files

path = <YOUR\_SHARE\_PATH>

browseable = yes

read only = no

guest ok = no

valid users = @<YOUR\_SHARE\_GROUP>

create mask = 0660

directory mask = 0770

force group = <YOUR\_SHARE\_GROUP>

Save the file and exit nano (Ctrl+O, Enter, Ctrl+X).

Check the configuration syntax for errors by running: testparm

#### E.6. Restart Samba

Run: sudo systemctl restart smbd nmbd Restarts samba with new configuration

#### E.7. Set Samba Password

Run: **sudo smbpasswd -a** <YOUR\_SAMBA\_USER> Set password for your samba user

### F) Client Shortcut Setup - Optional

Easy access to scripts on Windows - Skip if you prefer running .bat files directly.

#### F.1. Prepare Client Folder

Ensure **Start\_Server.bat**, **Stop\_Server.bat**, required .exe files, keys, and Icons folder are organised under <CLIENT\_CONTROL\_FOLDER\_PATH>.

#### F.2 Version A: Create Shortcuts

In a place of your choice, create a shortcut to execute the bat files for "start\_server" and "stop\_server" these will be your on/off buttons for your server. In this example we will create them on the desktop.

#### Create "Server On" shortcut

Right-click on your Desktop -> Create shortcut

Click "Browse" and chose: <CLIENT\_CONTROL\_FOLDER\_PATH>\Files\Start\_Server.bat

Example: C:\ServerControl\Files\Start\_Server.bat

Name the shortcut Start Server

Right-click 'Server On' shortcut -> properties -> shortcut

Choose "Server on.ico" -> click open -> ok

Click "Apply"

#### Create "Server Off" shortcut

Right-click on your Desktop -> Create shortcut

Click "Browse" and chose: <CLIENT\_CONTROL\_FOLDER\_PATH>\Files\Stop\_Server.bat

Example: C:\ServerControl\Files\Stop\_Server.bat

Name the shortcut Stop Server

Right-click 'Server On' shortcut -> properties -> shortcut

In Shortcut click "Change icon" -> Browse <CLIENT\_CONTROL\_FOLDER\_PATH> \lcons

Choose "Server off.ico" -> click open -> ok

Click "Apply"



#### F.2 Version B: Create & Pin Taskbar Shortcuts

This creates windows work-around allows special shortcuts designed for the taskbar

#### **Create the "Start Server" taskbar shortcut:**

- 1. Navigate to <CLIENT\_CONTROL\_FOLDER\_PATH>\lcons Create new shortcut
- 2. Copy and paste the line below into "Type the location of the item"

#### cmd.exe /c "<CLIENT\_CONTROL\_FOLDER\_PATH>\Files\Start\_Server.bat"

- 3. Click Next -> Name the shortcut: "Taskbar Start Server" -> Click Finish.
- 4. Right-click this new shortcut -> Properties -> Change Icon -> Click Browse
- 5. If made in the Icon folder you will see the "Server On".ico file use this file -> Click Ok -> Click Apply

Path to icon: <CLIENT\_CONTROL\_FOLDER\_PATH>\Icons\ and select "Server On" icon (.ico file).

7. Right-click on "Taskbar Start Server" -> pin to taskbar

#### Create the "Stop Server" taskbar shortcut:

- 1. Navigate to <CLIENT\_CONTROL\_FOLDER\_PATH>\lcons Create new shortcut
- 2. Copy and paste the line below into "Type the location of the item"

#### cmd.exe /c "<CLIENT CONTROL FOLDER PATH>\Files\Stop Server.bat"

- 3. Click Next -> Name the shortcut: "Taskbar Stop Server" -> Click Finish.
- 4. Right-click this new shortcut -> Properties -> Change Icon -> Click Browse
- 5. If made in the Icon folder you will see the "Server Off".ico file use this file -> Click Ok -> Click Apply

Path to icon: <CLIENT\_CONTROL\_FOLDER\_PATH>\Icons\ and select "Server Off" icon (.ico file).

7. Right-click on "Taskbar Stop Server" -> pin to taskbar





## G) Testing

#### **G.1. Test Power Off**

Use "Server Off" shortcut/pin. Verify server shuts down via SSH key.

#### G.2. Test Power On

Use "Server On" shortcut/pin. Verify server boots via WoL (wait boot time).

#### **G.3. Test File Share**

Map network drive on client using \\<YOUR\_SERVER\_HOSTNAME>.local\<YOUR\_SAMBA\_SHARE\_NAME> If that fails, try using \\<FINAL\_SERVER\_IP>\<YOUR\_SAMBA\_SHARE\_NAME> Use credentials <YOUR\_SAMBA\_USER> and the password set in E.7. Verify you can read/write files according to permissions.

The foundation laid by all the software engineers and coders that made this project possible for me to execute, I thank you.